

User Interface - Bug #4625

Frame configuration not shared or synched back to the GUI frame on redirection

04/22/2020 03:03 PM - Roger Borrello

Status:	New	Start date:	
Priority:	Normal	Due date:	
Assignee:		% Done:	0%
Category:		Estimated time:	0.00 hour
Target version:		case_num:	
billable:	No	version:	
vendor_id:	GCD		
Description			
Related issues:			
Related to User Interface - Feature #4164: implement misc UI features (frame ...			WIP

History

#1 - 04/22/2020 03:03 PM - Roger Borrello

- Related to Feature #4164: implement misc UI features (frame options, misc attributes) added

#2 - 04/22/2020 03:10 PM - Roger Borrello

During debug, I found that when the visible flag is set prior to the frame being displayed, the `getFrame(frameId)` returns `FrameGuiImpl`. After the frame is displayed, it returns `FrameChuiImpl`.

During the `f0` frame handling, the visible flag is found to be true in the `FrameChuiImpl`, so it's values for `FRAME-COL` and `FRAME-ROW` are returned correctly. But for all the other frames, it is left as false.

I am not familiar enough with why `FrameGuiImpl` is the frame class before the display, and `FrameChuiImpl` after, to know if that's working correctly. I do see when the frame is displayed, the visible in `FrameGuiImpl` is what is set.

I set a breakpoint in the client `FrameChuiImpl` and it shows `StreamableWidget.convertToStreamable -> FrameGuiImpl.convertToStreamable -> WidgetFactoryAdapter.ChuiWidgetFactory.create ...`

Testcase:

```
uast/frame_layout/frame_loc_attributes_get2-redirected.p
uast/frame_layout/frame_loc_attributes_get2.p
uast/frame_layout/frame_loc_attributes_helper.i
```

The helper takes a pre-processor directive for a log file. If it's there, it redirects. If it's not, it doesn't redirect.